

ICC PROFILE SET UP With The Color Profiling Kit

To achieve the best color quality possible when using Artsy Couture, please only use the ICC Profile we provide for soft proofing. We do not recommend that you convert your entire working profile to the ICC Profile provided. If you wish to proof in Photoshop complete the steps on pages 1-5. If you'd like to use Light Room, complete Step One, then skip to page 6 of this document.

Atep ()ne LOADING THE .ICC PROFILE IN PHOTOSHOP

Copy and paste the .icc file Artsy sent you via email into the specified areas listed below. The specified area is dependent on which computer platform you use, PC or Mac. If the file already exists on your computer, please replace it with this new file.

WINDOWS PLATFORM ///

Double click on the attached .icc file emailed to you by Artsy, and save this file to BOTH the following pathways:

C:/Windows/System32/Spool/drivers/color

C:/Program Files(x86)/Common Files/Adobe/Color/Profiles

MAC PLATFORM ///

If you are using Mac OS X:

Library/ColorSync/Profiles

Library/Application Support/Adobe/Color/Profiles

If you are using Mac OS 9:

System Folder/Color Sync/Profiles

System Folder/Application Support/Adobe/Color/Profiles

*some OS's will also require you to save the .icc file in Library/ColorSync/Profiles/Profiles

Congratulations! Profiles will automatically load when Photoshop is launched. You will need to repeat this step for the Metallic and Indigo (Press) profile as well.

Step Two PHOTOSHOP COLOR SETTINGS TO MATCH ARTSY COUTURE

Click Edit (located at the top left of the screen) then select the Color Settings option. When the pop up window opens, change the settings in the following fields:

WORK SPACE ///

- In the Working Spaces area beside the RGB option, please click on the drop down menu.
- Set the RGB to sRGB IEC61966-2.1.

COLOR MANAGEMENT POLICIES ///

- In the Color Management Policies area beside the RGB option, please click on the drop down menu.
- Set RGB to Preserve Embedded Profiles. CMYK and Gray can be set to OFF unless being used for other needs.
- Select Profile Mismatches: Ask When Opening and Ask When Pasting.
- Select Missing Profiles: Ask When Opening.

CONVERSION OPTIONS ///

- If you do not immediately see Conversion Options under Color Management Policies, click on the More Options button, located on the right of the Color Settings pop up window.
- In the **Engine** option, please choose either: **Adobe** or **Kodak**.
- In the Intent option, choose Perceptual.
 *Note: this will affect when profile conversions are applied.
- Uncheck the Black Point Compensation, Use Dither and Compensate for Scene options.


ADVANCED CONTROLS ///

- Make sure all options are unchecked.

Click the Save button, located on the right hand side of pop up screen. Save as: AC sRGB Generic Color. This helps avoid any confusion when needing to meet other printing specifications.

PLEASE NOTE: By saving these settings, they will now become your default, and will be set the same each time Photoshop is open.

Step Two (cont.) YOUR POP UP WINDOW SHOULD LOOK SIMILAR TO THE IMAGE BELOW.



Step Three SETTING UP PROOF COLORS FOR PHOTOSHOP

Click on View (located at the top left of the screen) then select the Proof Setup option, followed by Custom. When the pop up window opens, change the settings in the following fields:

DEVICE TO SIMULATE ///

- In the Device to Simulate area, click on the drop down menu and set it to AC-Lustre.icc.
- This is the ICC file from Step 1. You will need to repeat this step for the Metallic and Indigo (Press) profiles.
- Uncheck Preserve Color Numbers.

RENDERING INTENT ///

- In the Rendering Intent area, click on the drop down menu and set it to Perceptual.
- Check Black Point Compensation.

DISPLAY OPTIONS ///


- Uncheck both Simulate Paper Color and Simulate Ink Blank.

Click the **Save** button, located on the right hand side of pop up screen and save as: **AC-Lustre**. This helps avoid any confusion when needing to meet other printing specifications. You will need to repeat this step for both the Metallic and Indigo (Press) profiles.

The name of your setting will appear in the box next to the Custom Proof Condition box.

PLEASE NOTE: By saving these settings, they will now become your default, and will be set the same each time Photoshop is open.

YOUR POP UP WINDOW SHOULD LOOK SIMILAR TO THE IMAGE BELOW






When opening an image in Photoshop be certain to go to View > Proof Setup > AC Lustre

With the AC-Lustre.icc Profile selected (in the Device to Simulate box) the image will be changed to the print colors at Artsy Couture and for you to edit accordingly.

To view the difference between your original workspace and the AC Lustre proof:

- PC: Press Ctrl+Y
- Mac: Press Apple+Y

If Photoshop informs you that the image does not match the color profile when opening an image, please choose Convert Document's Colors to Working Space.



When editing is complete, click the **Save As** option to name your edited image. Never choose **Save** or you'll lose your original image!

YOU ARE NOW SOFT PROOFING IN PHOTOSHOP. HAVEFUN!



STEP 1

If you haven't already, go back to the first page of this document and complete Step 1.

STEP 2


When in Light Room, click the **Develop** tab (located at the top right of the screen), then check the **Soft Proof** box (on the lower left corner of the screen).





STEP 3

UNDER THE HISTOGRAM (located on the right of your screen) ///

- Next to Intent, select Perceptual and make sure Simulate Paper & Ink is unchecked.
- Click the arrows next to Profile and select Other.










STEP 4

All profiles downloaded into the Profiles folder will be displayed. Check all of the profiles you think you will need.

PLEASE NOTE: Only sRGB profiles can be used in Light Room. Light Room does not recognize CMYK profiles.



YOU ARE NOW SOFT PROOFING IN LIGHTROOM. HAVEFUN!